



BobCat CL Suite Software Installation from USB or CD

Use the following steps to install the BobCat CL Suite supplied on a USB or CD. Note that 'click' refers to the left mouse button.

1. If a version of BobCat CL Suite was previously installed on this machine, then you must first remove it:

To remove the application files:

- 1.1 Click on "Start".
- 1.2 Click on "Settings".
- 1.3 Click on "Control Panel".
- 1.4 Double click on "Add or Remove Programs" for Windows XP or "Programs and Features" for Windows Vista and Windows 7.
- 1.5 Click on "BobCat CameraLink".
- 1.6 Click on "Remove".
- 1.7 Click on "Bobcat Upload Manager".
- 1.8 Click on "Remove".
- 1.9 Click on the "Imperx Tool Kit".
- 1.10 Click on "Remove".
- 1.11 If the 'InstallShield Wizard' pops-up then follow the instructions on the screen and remove each application.

2. After having removed a previous version or if a version of BobCat CL Suite was NOT previously installed on this machine then:

The first step is to install the application files:

2.1 Insert the BobCat CL Suite software USB or CD into the appropriate drive; the setup.exe file will run automatically. Note: If it does not start automatically, click on "Start", "Run", enter or browse to "(USB or CD drive): setup.exe" and click "OK".

2.2 Wait for the "BobCat CL Suite Setup Wizard" screen to appear.



2.3 Follow the on-screen instructions.

2.4 Click "Finish". This completes the software installation.



2.5 Reboot your computer.

For additional information and the latest updates and downloads, please visit our website at www.imperx.com